## VideoCapture::VideoCapture

VideoCapture constructors.

C++: VideoCapture::VideoCapture()

C++: VideoCapture::VideoCapture(const string& filename)

C++: VideoCapture::VideoCapture(int device)

**Python:** cv2.**VideoCapture()**  $\rightarrow$  <**VideoCapture object>** 

 $\textbf{Python:} \ \, \text{cv2.VideoCapture} ( filename ) \rightarrow < \text{VideoCapture object} >$ 

**Python:** cv2. VideoCapture (device)  $\rightarrow$  < VideoCapture object>

C: CvCapture\* cvCaptureFromCAM(int device)

**Python:**  $cv.CaptureFromCAM(device) \rightarrow CvCapture$ 

C: CvCapture\* cvCaptureFromFile(const char\* filename)

**Python:** cv.CaptureFromFile(filename)  $\rightarrow CvCapture$ 

#### **Parameters**

**filename** – name of the opened video file

**device** – id of the opened video capturing device (i.e. a camera index). If there is a single camera connected, just pass 0.

**Note:** In C API, when you finished working with video, release CvCapture structure with cvReleaseCapture(), or use Ptr<CvCapture> that calls cvReleaseCapture() automatically in the destructor.

## VideoCapture::open

Open video file or a capturing device for video capturing

C++: bool VideoCapture::open(const string& filename)

C++: bool VideoCapture::open(int device)

 $\textbf{Python:} \ \, \texttt{cv2.VideoCapture.open} (filename) \rightarrow successFlag$ 

 $\textbf{Python:} \ \, \texttt{cv2.VideoCapture.open(device)} \rightarrow successFlag$ 

#### **Parameters**

**filename** – name of the opened video file

**device** – id of the opened video capturing device (i.e. a camera index).

The methods first call VideoCapture::release() to close the already opened file or camera.

# VideoCapture::isOpened

Returns true if video capturing has been initialized already.

C++: bool VideoCapture::isOpened()

**Python:** cv2.VideoCapture.**isOpened()**  $\rightarrow$  flag

If the previous call to VideoCapture constructor or VideoCapture::open succeeded, the method returns true.

## VideoCapture::release

Closes video file or capturing device.

 $\textbf{C++:} \ void \ \textbf{VideoCapture}:: \textbf{release()}$ 

Python: cv2.VideoCapture.release()

C: void cvReleaseCapture(CvCapture\*\* capture)

The methods are automatically called by subsequent VideoCapture::open() and by VideoCapture destructor.

The C function also deallocates memory and clears \*capture pointer.

# VideoCapture::grab

Grabs the next frame from video file or capturing device.

C++: bool VideoCapture::grab()

**Python:**  $cv2.VideoCapture.grab() \rightarrow successFlag$ 

C: int cvGrabFrame(CvCapture\* capture)

 $\textbf{Python:} \ \, \text{cv.GrabFrame}(\text{capture}) \rightarrow \text{int}$ 

The methods/functions grab the next frame from video file or camera and return true (non-zero) in the case of success.

The primary use of the function is in multi-camera environments, especially when the cameras do not have hardware synchronization. That is, you call VideoCapture::grab() for each camera and after that call the slower method VideoCapture::retrieve() to decode and get frame from each camera. This way the overhead on demosaicing or motion jpeg decompression etc. is eliminated and the retrieved frames from different cameras will be closer in time.

Also, when a connected camera is multi-head (for example, a stereo camera or a Kinect device), the correct way of retrieving data from it is to call *VideoCapture::grab* first and then call VideoCapture::retrieve() one or more times with different values of the channel parameter. See <a href="http://code.opencv.org/svn/opencv/trunk/opencv/samples/cpp/kinect\_maps.cpp">http://code.opencv.org/svn/opencv/trunk/opencv/samples/cpp/kinect\_maps.cpp</a>

# VideoCapture::retrieve

Decodes and returns the grabbed video frame.

C++: bool VideoCapture::retrieve(Mat& image, int channel=0)

**Python:** cv2.VideoCapture.retrieve([image[, channel]]) → successFlag, image

C: IplImage\* cvRetrieveFrame(CvCapture\* capture)

**Python:** cv.**RetrieveFrame**(capture) → iplimage

The methods/functions decode and return the just grabbed frame. If no frames has been grabbed (camera has been disconnected, or there are no more frames in video file), the methods return false and the functions return NULL pointer.

**Note:** OpenCV 1.x functions cvRetrieveFrame and cv.RetrieveFrame return image stored inside the video capturing structure. It is not allowed to modify or release the image! You can copy the frame using cvCloneImage() and then do whatever you want with the copy.

## VideoCapture::read

Grabs, decodes and returns the next video frame.

C++: VideoCapture& VideoCapture::operator>>(Mat& image)

C++: bool VideoCapture::read(Mat& image)

**Python:** cv2.VideoCapture.read([image]) → successFlag, image

C: IplImage\* cvQueryFrame(CvCapture\* capture)

**Python:** cv. QueryFrame (capture)  $\rightarrow$  iplimage

The methods/functions combine VideoCapture::grab() and VideoCapture::retrieve() in one call. This is the most convenient method for reading video files or capturing data from decode and return the just grabbed frame. If no frames has been grabbed (camera has been disconnected, or there are no more frames in video file), the methods return false and the functions return NULL pointer.

**Note:** OpenCV 1.x functions cvRetrieveFrame and cv.RetrieveFrame return image stored inside the video capturing structure. It is not allowed to modify or release the image! You can copy the frame using cvCloneImage() and then do whatever you want with the copy.

## VideoCapture::get

Returns the specified VideoCapture property

C++: double VideoCapture::get(int propId)

**Python:**  $cv2.VideoCapture.get(propId) \rightarrow retval$ 

C: double cvGetCaptureProperty(CvCapture\* capture, int propId)

**Python:** cv. **GetCaptureProperty**(capture, propId)  $\rightarrow$  double

### **Parameters**

**propId** – Property identifier. It can be one of the following:

- CV\_CAP\_PROP\_POS\_MSEC Current position of the video file in milliseconds or video capture timestamp.
- CV\_CAP\_PROP\_POS\_FRAMES 0-based index of the frame to be decoded/captured next.
- CV\_CAP\_PROP\_POS\_AVI\_RATIO Relative position of the video file: 0 start of the film, 1 end of the film.
- CV\_CAP\_PROP\_FRAME\_WIDTH Width of the frames in the video stream.
- CV\_CAP\_PROP\_FRAME\_HEIGHT Height of the frames in the video stream.
- CV CAP PROP FPS Frame rate.
- CV CAP PROP FOURCC 4-character code of codec.
- CV\_CAP\_PROP\_FRAME\_COUNT Number of frames in the video file.
- CV\_CAP\_PROP\_FORMAT Format of the Mat objects returned by retrieve().
- CV\_CAP\_PROP\_MODE Backend-specific value indicating the current capture mode.
- CV\_CAP\_PROP\_BRIGHTNESS Brightness of the image (only for cameras).

- CV\_CAP\_PROP\_CONTRAST Contrast of the image (only for cameras).
- CV\_CAP\_PROP\_SATURATION Saturation of the image (only for cameras).
- CV\_CAP\_PROP\_HUE Hue of the image (only for cameras).
- CV\_CAP\_PROP\_GAIN Gain of the image (only for cameras).
- CV CAP PROP EXPOSURE Exposure (only for cameras).
- CV\_CAP\_PROP\_CONVERT\_RGB Boolean flags indicating whether images should be converted to RGB.
- CV\_CAP\_PROP\_WHITE\_BALANCE Currently not supported
- CV\_CAP\_PROP\_RECTIFICATION Rectification flag for stereo cameras (note: only supported by DC1394 v 2.x backend currently)

**Note**: When querying a property that is not supported by the backend used by the VideoCapture class, value 0 is returned.

# VideoCapture::set

Sets a property in the VideoCapture.

C++: bool VideoCapture::set(int propertyId, double value)

**Python:**  $cv2.VideoCapture.set(propId, value) \rightarrow retval$ 

C: int cvSetCaptureProperty(CvCapture\* capture, int propId, double value)

**Python:** cv. **SetCaptureProperty** (capture, propId, value)  $\rightarrow$  None

### **Parameters**

**propId** – Property identifier. It can be one of the following:

- CV\_CAP\_PROP\_POS\_MSEC Current position of the video file in milliseconds.
- CV\_CAP\_PROP\_POS\_FRAMES 0-based index of the frame to be decoded/captured next.
- CV\_CAP\_PROP\_POS\_AVI\_RATIO Relative position of the video file: 0 start of the film, 1 end of the film.
- CV\_CAP\_PROP\_FRAME\_WIDTH Width of the frames in the video stream.
- CV\_CAP\_PROP\_FRAME\_HEIGHT Height of the frames in the video stream.
- CV\_CAP\_PROP\_FPS Frame rate.
- CV\_CAP\_PROP\_FOURCC 4-character code of codec.
- CV\_CAP\_PROP\_FRAME\_COUNT Number of frames in the video file.
- CV\_CAP\_PROP\_FORMAT Format of the Mat objects returned by retrieve().
- CV\_CAP\_PROP\_MODE Backend-specific value indicating the current capture mode.
- CV\_CAP\_PROP\_BRIGHTNESS Brightness of the image (only for cameras).
- **CV\_CAP\_PROP\_CONTRAST** Contrast of the image (only for cameras).
- CV\_CAP\_PROP\_SATURATION Saturation of the image (only for cameras).
- CV\_CAP\_PROP\_HUE Hue of the image (only for cameras).
- CV\_CAP\_PROP\_GAIN Gain of the image (only for cameras).

- CV\_CAP\_PROP\_EXPOSURE Exposure (only for cameras).
- CV\_CAP\_PROP\_CONVERT\_RGB Boolean flags indicating whether images should be converted to RGB.
- CV\_CAP\_PROP\_WHITE\_BALANCE Currently unsupported
- CV\_CAP\_PROP\_RECTIFICATION Rectification flag for stereo cameras (note: only supported by DC1394 v 2.x backend currently)

value – Value of the property.

## **VideoWriter**

### class VideoWriter

Video writer class.

### VideoWriter::VideoWriter

VideoWriter constructors

C++: VideoWriter::VideoWriter()

C++: VideoWriter::VideoWriter(const string& filename, int fource, double fps, Size frameSize, bool isColor=true)

**Python:** cv2.**VideoWriter**([filename, fourcc, fps, frameSize[, isColor]])  $\rightarrow$  <VideoWriter object>

C: CvVideoWriter\* cvCreateVideoWriter(const char\* filename, int fourcc, double fps, CvSize frameSize, int isColor=1)

**Python:** cv. CreateVideoWriter (filename, fource, fps, frameSize, isColor) → CvVideoWriter

**Python:** cv2.VideoWriter.**isOpened()**  $\rightarrow$  retval

**Python:** cv2.VideoWriter.open(filename, fource, fps, frameSize, isColor)  $\rightarrow$  retval

**Python:**  $cv2.VideoWriter.write(image) \rightarrow None$ 

### **Parameters**

**filename** – Name of the output video file.

**fourcc** – 4-character code of codec used to compress the frames. For example, CV\_FOURCC('P','I','M,'1') is a MPEG-1 codec, CV\_FOURCC('M','J','P','G') is a motion-jpeg codec etc.

**fps** – Framerate of the created video stream.

frameSize - Size of the video frames.

**isColor** – If it is not zero, the encoder will expect and encode color frames, otherwise it will work with grayscale frames (the flag is currently supported on Windows only).

The constructors/functions initialize video writers. On Linux FFMPEG is used to write videos; on Windows FFMPEG or VFW is used; on MacOSX QTKit is used.